Cockpit Enhancements

Enhancements in deployment flow

Cache Setup Flow


This section described the enhancements in cockpit-gdeploy plugin to handle lvmcache configuration

- **1-** In Gluster Deployment will have Check box based on Thinp check and will have one pop up.[Optional for User]
- 2- Below will be the fields which needs to be filled by User in pop up:

SSD: sdd

LV Size: XGB

-> If "Configure LV Cache" is unchecked then those two fields will be hidden.



Rest of the fields will be auto generated.

3- Then will make entry in gdeploy config file as:

[lv5]

action=setup-cache

ssd=sdd

vgname=gluster vg sdb or gluster vg vdb

poolname=gluster_thinpool_sdb or gluster_thinpool_vdb

cache lv=lvcache

cache lvsize=XGB

ignore lv errors=yes

cachemode=writethrough

4- Gdeploy will take care next.

Enable brick/volume creation via Cockpit

Users should be able to provision additional hosts and additional bricks post the initial 3 node deployment.

Consider following cases:

- 1. Additional disks attached to the existing 3 nodes
- 2. Additional host added to a RHHI deployment
 - a. Host is added to RHV-M via UI, hosted-engine can be deployed on hosts while adding the host.


In both of these cases, the RHV-M UI has capability to create brick from a storage device. This is limited to creating a single LV on brick though. I.e - raw device -> PV -> VG -> Thinpool -> LV. In order to be able to achieve flexibility in terms of attaching LVM cache, enabling dedupe/ compression - adding this to RHV-M via blivet modules will take considerable time.

Two options:


- 1. allow disk provisioning on storage devices via Cockpit UI.
- 2. Provide UI in RHV-M to generate and call an Ansible role on the hosts that will do the brick provisioning.

If we were to go with option 1, Cockpit UI needs to support this.

Complete Flow:




Gluster Management:




- -> This page will have Hosts, Bricks and Volumes informations.
- -> From here we can Expand Cluster, Expand Volume and Create Volume.


Expand Cluster:




-> Here we can expand our cluster by adding new Hosts.



-> Initially will have one volume, for more we can add more volumes by clicking on "Add Volume".




-> We can configure more bricks by using "Add bricks"




-> This will be the final screen after expand cluster.

Expand Volume:




-> For expand volume, will have to choose hosts present in cluster.





-> Here will have to choose volume and after that all related value will be populated which are readonly.




Create Volume:








Asymmetric brick configuration:



- -> In brick configuration will have "Tab" for Hosts and Host wise you can change Device.
- -> Default all the fields will be read only except "Device Name"
- -> If the volume is "Arbiter" then "Size" field will be writable.

• Changing Device in Host3 and also volume is "Arbiter":



-> Here Host3 device is "sdc".